



Prerequisites


1. Install Python 3.10+ (64-bit)
2. Install Git
3. Install ffmpeg and add it to PATH (verify ffmpeg -version)

Recording Setup


1. OBS Recorder
 1. <https://github.com/obsproject/obs-websocket/releases>
 2. Using the installer (recommended): download obs-websocket-4.9.1-compat-Qt6-Windows-Installer.exe, launch it and follow the instructions.
 3. Using the obs-websocket-4.9.1-compat-Qt6-Windows.zip archive : copy the contents of the archive to the root of your OBS Studio installation folder (C:\Program Files\obs-studio).
 4. Modify default settings to match the given settings




5. In Tools → Websocket Server Settings (4.x Compact) → Set server port to 4444 and leave password empty



6. Add Scene, Sources, and Audio Mixer as shown if not already present





Installing the Chrome Extension

1. Open Chrome → `chrome://extensions`.
2. Toggle Developer mode (top right).
3. Click Load unpacked → pick “web_logger” folder (contains manifest.json).
4. Make sure it's enabled and has access to “On all sites”.

Code

1. Run VS Code as Administrator
2. Clone github repo <https://github.com/gmananya/computer-use-logger>
3. Install all packages from requirement.txt

Start Recording

1. Keep OBS recorder app open
2. In terminal, run python [main.py](#)
3. Pick task set and task #, then click “Start logging”
4. Data goes to `task_logs/{task_number}/` and `task_logs/{task_number}/web_logs/`

Stop Recording

1. Click on “Stop recording”

For Replay Setup

1. In a terminal, do `cd replay → python replay_server.py`
2. Change the task you would like to replay by changing the `DEFAULT_TASK = "{task_number}"` in `replay_local.py`
3. Save the changes
4. In another terminal, do `cd replay → python replay_local.py`